

STRESS FREE COMFORT BALM

LS240330

Find your moment of Zen with our Stress-Free Comfort Balm. This calming balm is a gentle companion in your daily routine, designed to soothe the skin and provide a peaceful respite from the day's stressors.

PHASE	%	TRADENAME	INCI
А	85.87	Water	Water
А	0.10	Dermofeel PA-12	Sodium Phytate
А	0.01	Aloe Vera 1X	Aloe Barbadensis Leaf Juice
А	0.40	Ultrez-10	Carbomer
А	2	Glycerin 99.7%	Glycerin
А	0.065	Sodium Hydroxide 50% solution	Sodium Hydroxide
В	1	Lipocol C	Cetyl Alcohol
В	3	Olivoil Glutamate	Cetearyl Alcohol, Glyceryl Stearate, Sodium Olivoyl Glutamate, Aqua, Potassium Sorbate, Sodium Benzoate, Benzyl Alcohol
В	3.1	Lipocol GC	Caprylic/Capric Triglyceride
В	1	Surfacare S	Oleic/Linoleic/Linolenic Polyglycerides
В	1	Zenibee Cream	Octyldodecanol, Beeswax
С	1	Devecide CP	Phenoxyethanol, Chlorphenesin
С	0.2	Natura-Tec Marine Oceanmist CL CH	Caprylic/Capric Triglyceride and Cholesterol and Eicosapentaenoic acid and ß-sitosterol
С	0.4	BGT TDP-1	Tridecapeptide-1 and Peptylene Glycol and Water
С	0.7	Beraca CBA	Copaifera Officinalis (balsam copaiba) Resin (and) Passiflora Edulis Seed Oil (and) Tocopherol
D	0.1	Water	Water
D	0.05	Kalibiome Sensitive	Lactobacillus ferment, Mannitol

Deveraux Specialties, LLC 12835 Arroyo St. Sylmar, CA 91342

www.DeverauxSpecialties.com

+1 (818) 837-3700 info@DeverauxSpecialties.com



PROCEDURE

- 1. While heating Water to 70-75°C, add Dermofeel and Aloe Vera to Water until all is dissolved. Sprinkle Ultrez-10 with moderate mixing and make sure Ultrez is dispersed, then add the remaining ingredients of Phase A to batch.
- 2. Heat Phase B with slow mixing to 70-75°C until all is melted.
- 3. When both phases at 70-75°C, add Phase B to Phase A and mix well until uniform. Start cooling.
- 4. At 35-40°C, add Phase C and pre-blended Phase D to batch with continued mixing while cooling to 25-30°C.

Deveraux Specialties, LLC 12835 Arroyo St. Sylmar, CA 91342 www.DeverauxSpecialties.com

+1 (818) 837-3700 info@DeverauxSpecialties.com